LASSI Data Analysis Pipeline V2

February 28, 2019

1 LASSI Data Analysis Pipeline V2

This is an updated attempt to create a pipeline that illustrates how one would take Leica scanner data and produce commands to the Active Surface Manager that would compensate for any detected surface deformations. The parts of this pipeline that need work we'll mark in red TODOs.

```
In [11]: # %matplotlib notebook
```

1.1 Step One: Get some Leica data for a reference and signal scan

We are still unclear on how we are going to do this for production. What we are currently using as input are PTX files (human readable) that were produced by Leica employees (using in part at least, the Cyclone software).

Copies of these files can be in: /home/sandboxes/pmargani/LASSI/data.

According to Brian Elbe, all he did to produce these files was import the data into Cyclone, removed 'unwanted' parts of the image (presumably the ground), then export it to PTX. Should be easy to replicate.

The files are further processed by our own Mathematica code that was adapted from some of Fred's work.

This code does a simple Affine Transform, and filters out things like the header and data that is past a certain distance from the scanner. It can also optionally take a random sample of the PTX data to avoid working with the full data set.

It will write the final output to a file name of your choosing.

The source for this can be found here: /home/sandboxes/pmargani/LASSI/data/LeicaP40demo/Aug2016/

TODO: We are currenlty porting this to Python, but are hung up on a question we need answered from Fred.

1.2 Step Two: Smooth this Data

Warning: this is the computationally expensive part! We've already done this step, which takes about 10 hours for each scan, so we highly recommend you don't run this commented code, and instead use the dumps we made of this smoothing to file.

TODO: we need to find a way to make this processing faster by this summer (2019).

```
#n = 512
#fn1 = "data/randomSampleSta10.csv"
#x1, y1, z1 = smoothSpherical(fn1, n)
#fn2 = "data/randomSampleBumpScan14.csv"
#x2, y2, z2 = smoothSpherical(fn2, n)

# instead the smoothed data can be found here:
# fn1 = "data/BumpScan.csv.smoothed.sig.001.all.npz"
# fn = "data/Baseline_STA10_HIGH_METERS.csv.smoothed.sig.001.all.npz"
```


1.3 Step Three: Fit this data to parabolas


We'll leverage our parabolas module to do the heavy lifting here. See also the 'Parabolas' and 'Show me the Bumps' Notebooks.


We also have a unit test class, TestParabolas.py, which demonstrates the limits of our parabolas toolbox.


```
In [13]: from parabolas import *
    fn = "data/Baseline_STA10_HIGH_METERS.csv.smoothed.sig.001.all.npz"
    refDiff, refX, refY = fitLeicaScan(fn)
```

cleaned data fitted with coefficients: [5.74103825e+01 2.83550388e-01 -2.22811412e+00 -4.9179 1.52444697e-03 -3.31407039e-02]













cleaned data fitted with coefficients: [5.74057921e+01 2.87711772e-01 -2.22274546e+00 -4.9178 1.43249224e-03 -3.30739453e-02]












1.4 Step Four: Regrid the data to both be in the same evenly spaced x, y

Both so that both scans are in the same x, y space, and also in preparation for fitting zernikes to the results, we need to regrid our scans. They were evenly spaced in spherical coordinated, but are now unevenly spaced in x, y, which is why the images above look like guitar picks and not dishes. This is the problem we are fixing in this step.






In [7]: imagePlot(bumpDiffs, "bump scan smoothed")




These images don't tell us much, but if we were to smooth the log of the difference of one of these scans, we'll see a familiar image:

1.5 Step Five: Find the Deformations

Also known as, 'Show me the Bumps'. This step is conceptually simple: we just find the difference between our reference and signal scan. We break it out in a separate step here for dramatic affect.







Step five and a half: open some beers.

1.6 Step Six: Fit Zernikes to this surface

This is identical to what we did in the first version of our pipeline. But note, that we're still not sure that we want to do this on this data: we probably need put this image on a unit circle? TODO: Determine what else might need to be done to image before fitting zernikes.





Zernike Polynomials List

1	Z1	Ι	Z2		Z3		Z4		Z5		Z6		Z7		Z8		Z9		 Z:	10	1
1		•		•		•		•		•		•		·	0.072	•		1	0.0)27	1
															Z18			1	Z2	20	
1	0.365	-	0.182	-	-0.067	-	0.037		0.015		0.074	-	0.025	.	-0.053		0.023	1	0.0)30	
1	Z21	1	Z22		Z23	1	Z24		Z25		Z26	1	Z27		Z28		Z29	1	Z3	30	
-	0.097	1	0.540		0.080	-	0.100	-	-0.021	-	-0.057	-	0.014	.	-0.014		0.118	1	0.0)48	
1	Z31	1	Z32		Z33	1	Z34		Z35		Z36	1	Z37								
-	0.080	-	0.078		0.090	-	0.027		0.013	-	-0.020		0.000								

fitlist: [0, 0, -0.306, 0.171, 0.468, -0.028, -0.309, -0.153, 0.072, 0.053, 0.027, 0.365, -0.18

Z2 = -0.306 Z11 x Tilt

Z3 = 0.171 Z11 y Tilt

Z4 = 0.468 Z20 Defocus

- Z5 = -0.028 Z22 Primary Astigmatism at 45
- Z6 = -0.309 Z22 Primary Astigmatism at 0
- Z7 = -0.153 Z31 Primary y Coma
- Z8 = 0.072 Z31 Primary x Coma
- Z9 = 0.053 Z33 y Trefoil
- $Z10 = 0.027 \ Z33 \ x \ Trefoil$
- Z11 = 0.365 Z40 Primary Spherical
- Z12 = -0.182 Z42 Secondary Astigmatism at 0
- Z13 = -0.067 Z42 Secondary Astigmatism at 45
- Z14 = -0.037 Z44 x Tetrafoil
- Z15 = 0.015 Z44 y Tetrafoil
- Z16 = 0.074 Z51 Secondary x Coma
- Z17 = -0.025 Z51 Secondary y Coma
- Z18 = -0.053 Z53 Secondary x Trefoil
- Z19 = 0.023 Z53 Secondary y Trefoil
- $Z20 = 0.03 Z55 \times Pentafoil$
- Z21 = -0.097 Z55 y Pentafoil
- Z22 = 0.54 Z60 Secondary Spherical
- Z23 = 0.08 Z62 Tertiary Astigmatism at 45
- Z24 = -0.1 Z62 Tertiary Astigmatism at 0
- Z25 = -0.021 Z64 Secondary x Trefoil
- Z26 = -0.057 Z64 Secondary y Trefoil
- Z27 = -0.014 Z66 Hexafoil Y
- Z28 = -0.014 Z66 Hexafoil X
- Z29 = 0.118 Z71 Tertiary y Coma
- Z30 = 0.048 Z71 Tertiary x Coma
- Z31 = -0.08 Z73 Tertiary y Trefoil
- Z32 = -0.078 Z73 Tertiary x Trefoil
- Z33 = 0.09 Z75 Secondary Pentafoil Y
- Z34 = -0.027 Z75 Secondary Pentafoil X
- Z35 = 0.013 Z77 Heptafoil Y
- Z36 = -0.02 Z77 Heptafoil X
- Z2 = -0.306 Z11 x Tilt
- Z3 = 0.171 Z11 y Tilt
- Z4 = 0.468 Z20 Defocus
- $Z5 = -0.028 \ Z22 \ Primary \ Astigmatism at 45$
- Z6 = -0.309 Z22 Primary Astigmatism at 0
- Z7 = -0.153 Z31 Primary y Coma
- Z8 = 0.072 Z31 Primary x Coma
- Z9 = 0.053 Z33 y Trefoil
- $Z10 = 0.027 Z33 \times Trefoil$
- Z11 = 0.365 Z40 Primary Spherical
- Z12 = -0.182 Z42 Secondary Astigmatism at 0
- Z13 = -0.067 Z42 Secondary Astigmatism at 45
- Z14 = -0.037 Z44 x Tetrafoil
- Z15 = 0.015 Z44 y Tetrafoil
- Z16 = 0.074 Z51 Secondary x Coma
- Z17 = -0.025 Z51 Secondary y Coma

```
Z18 = -0.053 Z53 Secondary x Trefoil
Z19 = 0.023 Z53 Secondary y Trefoil
Z20 = 0.03 Z55 \times Pentafoil
Z21 = -0.097 Z55 y Pentafoil
Z22 = 0.54 Z60 Secondary Spherical
Z23 = 0.08 Z62 Tertiary Astigmatism at 45
Z24 = -0.1 Z62 Tertiary Astigmatism at 0
Z25 = -0.021 Z64 Secondary x Trefoil
Z26 = -0.057 Z64 Secondary y Trefoil
Z27 = -0.014 Z66 Hexafoil Y
Z28 = -0.014 Z66 Hexafoil X
Z29 = 0.118 Z71 Tertiary y Coma
Z30 = 0.048 Z71 Tertiary x Coma
Z31 = -0.08 Z73 Tertiary y Trefoil
Z32 = -0.078 Z73 Tertiary x Trefoil
Z33 = 0.09 Z75 Secondary Pentafoil Y
Z34 = -0.027 Z75 Secondary Pentafoil X
Z35 = 0.013 Z77 Heptafoil Y
Z36 = -0.02 Z77 Heptafoil X
```



1.7 Step Seven: Convert the coefficients from Noll to ANSI

Recall that opticspy works in Noll notation, while the Active Surface Manager seems to work in a modified version of ANSI (offset by one, phase rotated by 90 degrees). Whether this is the only conversion needed to be done is another remaining open question.

```
In [10]: from zernikeIndexing import noll2asAnsi, printZs
    # why does the fitlist start with a zero? for ZO?? Anyways, avoid it
    nollZs = fitlist[1:(numZsFit+1)]
    asAnsiZs = noll2asAnsi(nollZs)
    print "nolZs"
    printZs(nollZs)
    print "active surface Zs"
    printZs(asAnsiZs)
nolZs
[0]
[-0.306, 0.171]
[0.468, -0.028, -0.309]
[-0.153, 0.072, 0.053, 0.027]
```

```
[0.365, -0.182, -0.067, -0.037, 0.015]
[0.074, -0.025, -0.053, 0.023, 0.03, -0.097]
[0.54, 0.08, -0.1, -0.021, -0.057, -0.014, -0.014]
[0.118, 0.048, -0.08, -0.078, 0.09, -0.027, 0.013, -0.02]
active surface Zs
[0]
[-0.306, 0.171]
[-0.309, 0.468, -0.028]
[0.027, 0.072, -0.153, 0.053]
[-0.037, -0.182, 0.365, -0.067, 0.015]
[0.03, -0.053, 0.074, -0.025, 0.023, -0.097]
[-0.014, -0.057, -0.1, 0.54, 0.08, -0.021, -0.014]
[-0.02, -0.027, -0.078, 0.048, 0.118, -0.08, 0.09, 0.013]
```

1.8 Step Eight: Send these Coefficients to the Active Surface Manager

The Active Surface Manager has the zernike_coeff parameter (indexes 1 through N). When these are set, the manager can use them to compute the displacement of each individual actuator.

However, one has to have everything setup correctly and have the right permissions, so we won't simply call it from here. Instead, here's the instructions: * save asAnsiZs to numpy file * decide which telescope you want to use (real, sim?) * use the new ActiveSurfaceDevice.py here: /home/sandboxes/pmargani/sparrow/master3/sparrow/gbt/api/ygor/src * python ActiveSurfaceDevice.py

In []: